

Ubiquiti - USG disable NAT

1. **ssh <adminusername>@<IP of USG LAN>**
2. type **'configure'**
3. type **'show service nat'** #you should see rule 6001, 6002, 6003 by default
4. type **'set service nat rule 6001 disable'** #disables corporate network NAT
5. type **'set service nat rule 6002 disable'** #disables remote user network NAT
6. type **'set service nat rule 6003 disable'** #disables guest network NAT
7. type **'compare'** #just to see if you did things right
8. type **'commit'**
9. type **'save'**
10. type **'mca-ctrl -t dump-cfg > config.gateway.json'**
11. copy this file over to your Unifi controller,
.'scp config.gateway.json root@<controller_IP>:/usr/lib/unifi/data/sites/{ {site folder} }/config.gateway.json'

Revision #1

Created 21 March 2020 13:07:42 by Michael Cleary

Updated 16 February 2022 23:28:01 by Michael Cleary